F02BBF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

F02BBF calculates selected eigenvalues and eigenvectors of a real symmetric matrix by reduction to tridiagonal form, bisection and inverse iteration, where the selected eigenvalues lie within a given interval.

2 Specification

```
SUBROUTINE F02BBF(A, IA, N, ALB, UB, M, MM, R, V, IV, D, E, E2, X,

G, C, ICOUNT, IFAIL)

INTEGER

IA, N, M, MM, IV, ICOUNT(M), IFAIL

real

A(IA,N), ALB, UB, R(M), V(IV,M), D(N), E(N),

E2(N), X(N,7), G(N)

LOGICAL

C(N)
```

3 Description

The real symmetric matrix A is reduced to a symmetric tridiagonal matrix T by Householder's method. The eigenvalues which lie within a given interval [l, u], are calculated by the method of bisection. The corresponding eigenvectors of T are calculated by inverse iteration. A back-transformation is then performed to obtain the eigenvectors of the original matrix A.

4 References

[1] Wilkinson J H and Reinsch C (1971) Handbook for Automatic Computation II, Linear Algebra Springer-Verlag

5 Parameters

1: A(IA,N) - real array

Input/Output

On entry: the lower triangle of the n by n symmetric matrix A. The elements of the array above the diagonal need not be set.

On exit: the elements of A below the diagonal are overwritten, and the rest of the array is unchanged.

2: IA — INTEGER

On entry: the first dimension of the array A as declared in the (sub)program from which F02BBF is called.

Constraint: IA \geq N.

3: N — INTEGER Input

On entry: n, the order of the matrix A.

4: ALB - real

5: UB-real

On entry: l and u, the lower and upper end-points of the interval within which eigenvalues are to be calculated.

6: M — INTEGER Input

On entry: an upper bound for the number of eigenvalues within the interval.

[NP3086/18/pdf] F02BBF.1

7: MM — INTEGER Output

On exit: the actual number of eigenvalues within the interval.

8: R(M) — real array Output

On exit: the eigenvalues, not necessarily in ascending order.

9: V(IV,M) - real array

Output

On exit: the eigenvectors, stored by columns. The ith column corresponds to the ith eigenvalue. The eigenvectors are normalised so that the sum of the squares of the elements are equal to 1.

10: IV — INTEGER Input

On entry: the first dimension of the array V as declared in the (sub)program from which F02BBF is called.

Constraint: $IV \geq N$.

11: D(N) — real array Workspace

12: E(N) — real array Workspace

13: E2(N) — real array Workspace

14: X(N,7) - real array Workspace

15: G(N) - real array Workspace

16: C(N) — LOGICAL array Workspace

17: ICOUNT(M) — INTEGER array

Output

On exit: ICOUNT(i) contains the number of iterations for the ith eigenvalue.

18: IFAIL — INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

Errors detected by the routine:

IFAIL = 1

M is less than the number of eigenvalues in the given interval. On exit MM contains the number of eigenvalues in the interval. Rerun with this value for M.

IFAIL = 2

More than 5 iterations are required to determine any one eigenvector.

7 Accuracy

There is no guarantee of the accuracy of the eigenvectors as the results depend on the original matrix and the multiplicity of the roots. For a detailed error analysis see Wilkinson and Reinsch [1] pp 222 and 436.

8 Further Comments

The time taken by the routine is approximately proportional to n^3 .

This subroutine should only be used when less than 25% of the eigenvalues and the corresponding eigenvectors are required. Also this subroutine is less efficient with matrices which have multiple eigenvalues.

F02BBF.2 [NP3086/18/pdf]

9 Example

To calculate the eigenvalues lying between -2.0 and 3.0, and the corresponding eigenvectors of the real symmetric matrix:

 $\begin{pmatrix}
0.5 & 0.0 & 2.3 & -2.6 \\
0.0 & 0.5 & -1.4 & -0.7 \\
2.3 & -1.4 & 0.5 & 0.0 \\
-2.6 & -0.7 & 0.0 & 0.5
\end{pmatrix}$

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
FO2BBF Example Program Text
  Mark 14 Revised. NAG Copyright 1989.
   .. Parameters ..
   INTEGER
                    NMAX, MMAX, IA, IV
  PARAMETER
                     (NMAX=8, MMAX=8, IA=NMAX, IV=NMAX)
   INTEGER
                    NIN, NOUT
  PARAMETER
                     (NIN=5, NOUT=6)
   .. Local Scalars ..
  real
                    RLB, RUB
   INTEGER
                    I, IFAIL, J, M, MM, N
   .. Local Arrays ..
  real
                    A(IA, NMAX), D(NMAX), E(NMAX), E2(NMAX), G(NMAX),
                    R(MMAX), V(IV, MMAX), X(NMAX, 7)
   INTEGER
                    ICOUNT (MMAX)
  LOGICAL
                    C(NMAX)
   .. External Subroutines ..
  EXTERNAL
                    F02BBF
   .. Executable Statements ..
   WRITE (NOUT,*) 'F02BBF Example Program Results'
   Skip heading in data file
   READ (NIN,*)
  READ (NIN,*) N, M
  WRITE (NOUT,*)
   IF (N.LT.1 .OR. N.GT.NMAX .OR. M.LT.1 .OR. M.GT.MMAX) THEN
      WRITE (NOUT,99999) 'N or M out of range: N = ', N, ' M = ', M
      STOP
  END IF
  READ (NIN, *) RLB, RUB, ((A(I,J),J=1,N),I=1,N)
   IFAIL = 1
   CALL FO2BBF(A, IA, N, RLB, RUB, M, MM, R, V, IV, D, E, E2, X, G, C, ICOUNT, IFAIL)
   IF (IFAIL.NE.O) THEN
      WRITE (NOUT, 99999) 'Error in FO2BBF. IFAIL =', IFAIL
      WRITE (NOUT,*) 'Eigenvalues'
      WRITE (NOUT,99998) (R(I),I=1,MM)
      WRITE (NOUT,*)
      WRITE (NOUT,*) 'Eigenvectors'
      DO 20 I = 1, N
         WRITE (NOUT, 99998) (V(I, J), J=1, MM)
20
      CONTINUE
  END IF
  STOP
```

[NP3086/18/pdf] F02BBF.3

```
99999 FORMAT (1X,A,I5,A,I5)
99998 FORMAT (1X,8F9.4)
END
```

9.2 Program Data

```
F02BBF Example Program Data

4 3

-2.0 3.0

0.5 0.0 2.3 -2.6

0.0 0.5 -1.4 -0.7

2.3 -1.4 0.5 0.0

-2.6 -0.7 0.0 0.5
```

9.3 Program Results

FO2BBF Example Program Results

```
Eigenvalues -1.0000 2.0000
```

Eigenvectors

-0.1000 -0.1000 -0.7000 -0.7000 -0.5000 0.5000 -0.5000 0.5000

F02BBF.4 (last) [NP3086/18/pdf]